

Current driver versions:

COM Port Redirector Plug & Play

Com-Servers under Windows XP/7/8/8.1/10/11 incl. 64-bit- and Server-Editions

Connect a Com-Server or a Web-IO with serial interface to the network, establish a virtual COM port on your system and your serial application is network-capable; without having to program a single line of code.

Date	Changes and comments	Revision
February 8, 2024	<ul style="list-style-type: none"> Security fix: Unquoted ImagePath in the registry corrected (VDE-2024-018) 	4.43 EXE download (approx. 15.8 MB)
October 4, 2023	<ul style="list-style-type: none"> Fixed: Changes to the logging level only took effect after a Windows restart New: Logging can be completely disabled Fixed: Behavior when installations are cancelled/failed 	4.42 EXE download (approx. 15.8 MB)
March 16, 2022	<ul style="list-style-type: none"> Individually available Windows access rights for the configuration file Optical corrections in the configuration tool Elimination of support for Windows Vista and Server 2008 (since Version 4.40) 	4.41 EXE download (approx. 15.6 MB)
January 14, 2022	<ul style="list-style-type: none"> NEW: Optional encryption of network connections per TLS-PSK for Com-Server models 58665, 58662, 58664, 58669 having firmware version 1.54 or higher Any handshake setting differing from the current Com-Server configuration were not set until the COM port was closed Various cosmetic improvements to the Config tool Elimination of support for Windows Vista and Server 2008 beginning with this version 	4.40 EXE download (approx. 15.6 MB)
July 9, 2020	<ul style="list-style-type: none"> HLK certified version for Windows 10 and Server 2016/2019 	4.35 EXE download (approx. 16.01 MB)
June 24, 2019	<ul style="list-style-type: none"> Options for preventing serial devices from being incorrectly interpreted as a mouse 	4.34 EXE download (approx. 9.18 MB)
April 6, 2018	<ul style="list-style-type: none"> Installation problem on unpatched Win7 systems fixed Improved operation under XP/Server 2013 	4.33 EXE download (approx. 9.19 MB)
September 20, 2017	<ul style="list-style-type: none"> Installation problem under Win 8.1/2012R2 fixed 	4.31 EXE download (approx. 9.41 MB)
August 30, 2017	<ul style="list-style-type: none"> Attestation signing (fixes problems with current Win 10 versions in conjunction with Secure Boot) 	4.30 EXE download (approx. 8.93 MB)
August 9, 2017	<ul style="list-style-type: none"> Optimizations for silent installations Optimizations for the Portmap tool 	4.29 EXE download (approx. 8.68 MB)
January 3, 2017	<ul style="list-style-type: none"> Optimizing of failed reconnects when there is simultaneous data sending SHA256 signature for the installation exe Cosmetic corrections for the version information details 	4.26 EXE download (approx. 8.83 MB)
October 26, 2016	<ul style="list-style-type: none"> Optimized start behavior Cosmetic corrections in Config tool 	4.24 EXE download (approx. 8.78 MB)
June 14, 2016	<ul style="list-style-type: none"> Optimized connection handling for NAT connected virtual machines Firewall-optimized reconnect after connection interruptions 	4.23 EXE - approx. 8.56MB <i>[on request]</i>

Date	Changes and comments	Revision
July 24, 2015	<ul style="list-style-type: none"> Port management in configuration tool corrected (deleting, creating, applying) 	4.21 EXE - approx. 8.76MB <i>[on request]</i>
January 5, 2015	<ul style="list-style-type: none"> Installation optimized Corrections/additions to the optional tools Companion and Portmap Setup of virtual COM ports optimized 	4.20 EXE - approx. 8.76MB <i>[on request]</i>
June 30, 2014	<ul style="list-style-type: none"> Serial API: Event handling revised/corrected Optional baud rate-dependent write delay corrected Cosmetic corrections in Config tool and Companion 	4.12 EXE - approx. 8.37MB <i>[on request]</i>
April 30, 2014	<ul style="list-style-type: none"> New setup as *.exe with language option DNS resolution improved Rare bluescreen mainly in virtual environments fixed 	4.10 EXE - approx. 8.34MB <i>[on request]</i>
March 10, 2014	<ul style="list-style-type: none"> Setup Helper revised Signature for 32-bit drivers Cosmetic correction to PortMap 	4.06 MSI - approx. 4.46 MB <i>[on request]</i>
September 12, 2013	<ul style="list-style-type: none"> Display of the application that opens a COM port in Portmap Portmap installation optimized Context help revised 	4.04 MSI - approx. 4.35 MB <i>[on request]</i>
April 9, 2013	<ul style="list-style-type: none"> Null terminating of the registry data in DeviceMap/SerialComm 	4.03 MSI - approx. 4.3 MB <i>[on request]</i>
February 4, 2013	<ul style="list-style-type: none"> Buffer handling for read requests optimized 	4.02 MSI - approx. 4.3 MB <i>[on request]</i>
January 15, 2013	<ul style="list-style-type: none"> COM Port Redirector integrated into plug-and-play system 	4.01 MSI - approx. 4.3 MB <i>[on request]</i>



We are available to you in person:

Wiesemann & Theis GmbH
Porschestra. 12
42279 Wuppertal
Phone: +49 202/2680-110 (Mon.-Fri. 8 a.m. to 5 p.m.)
Fax: +49 202/2680-265
info@wut.de

© Wiesemann & Theis GmbH, subject to mistakes and changes: Since we can make mistakes, none of our statements should be applied without verification. Please let us know of any errors or misunderstandings you find so that we can become aware of and eliminate them.

[Data Privacy](#)